

◇ LANGUAGE

FUNCTIONS

VARIABLES

STRUCTURE

LIBRARIES

GLOSSARY

The Arduino Reference text is licensed under a [Creative Commons Attribution-Share Alike 3.0 License](#).

Find anything that can be improved? [Suggest corrections and new documentation via GitHub](#).

Doubts on how to use Github? Learn everything you need to know in [this tutorial](#).

Reference > Language > Functions > External interrupts > Attachinterrupt

attachInterrupt()

[External Interrupts]

Description

Digital Pins With Interrupts

The first parameter to **attachInterrupt()** is an interrupt number. Normally you should use **digitalPinToInterrupt(pin)** to translate the actual digital pin to the specific interrupt number. For example, if you connect to pin 3, use **digitalPinToInterrupt(3)** as the first parameter to **attachInterrupt()**.

BOARD	DIGITAL PINS USABLE FOR INTERRUPTS
Uno, Nano, Mini, other 328-based	2, 3
Uno WiFi Rev.2	all digital pins
Mega, Mega2560, MegaADK	2, 3, 18, 19, 20, 21
Micro, Leonardo, other 32u4-based	0, 1, 2, 3, 7
Zero	all digital pins, except 4



101

all digital pins (Only pins 2, 5, 7, 8, 10, 11, 12, 13 work with **CHANGE**)

Notes and Warnings

Note

Inside the attached function, `delay()` won't work and the value returned by `millis()` will not increment. Serial data received while in the function may be lost. You should declare as **volatile** any variables that you modify within the attached function. See the section on ISRs below for more information.

Using Interrupts

Interrupts are useful for making things happen automatically in microcontroller programs, and can help solve timing problems. Good tasks for using an interrupt may include reading a rotary encoder, or monitoring user input.

If you wanted to insure that a program always caught the pulses from a rotary encoder, so that it never misses a pulse, it would make it very tricky to write a program to do anything else, because the program would need to constantly poll the sensor lines for the encoder, in order to catch pulses when they occurred. Other sensors have a similar interface dynamic too, such as trying to read a sound sensor that is trying to catch a click, or an infrared slot sensor (photo-interrupter) trying to catch a coin drop. In all of these situations, using an interrupt can free the microcontroller to get some other work done while not missing the input.

About Interrupt Service Routines

Last Update: 3/22/2019

[EDIT THIS PAGE](#)

[SIGN IN](#) [HOME](#) [STORE](#) [SOFTWARE](#) [EDUCATION](#) [RESOURCES](#) [COMMUNITY](#) [HELP](#)

increment inside an ISR. Since `delay()` requires interrupts to work, it will not work if called inside an ISR. `micros()` works initially, but will start behaving erratically after 1-2 ms.

`delayMicroseconds()` does not use any counter, so it will work as normal.

Typically global variables are used to pass data between an ISR and the main program. To make sure variables shared between an ISR and the main program are updated correctly, declare them as `volatile`.

For more information on interrupts, see [Nick Gammon's notes](#).

Syntax

`attachInterrupt(digitalPinToInterrupt(pin), ISR, mode);` (recommended)

`attachInterrupt(interrupt, ISR, mode);` (not recommended)

`attachInterrupt(pin, ISR, mode);` (Not recommended. Arduino SAMD Boards, Uno WiFi Rev2, Due, 101 only)

Parameters

interrupt: the number of the interrupt (`int`)

pin: the pin number

ISR: the ISR to call when the interrupt occurs; this function must take no parameters and return nothing. This function is sometimes referred to as an interrupt service routine.

mode: defines when the interrupt should be triggered. Four constants are predefined as valid values:

- **LOW** to trigger the interrupt whenever the pin is low,
- **CHANGE** to trigger the interrupt whenever the pin changes value
- **RISING** to trigger when the pin goes from low to high,

Returns

Nothing

Example Code

```
const byte ledPin = 13;
const byte interruptPin = 2;
volatile byte state = LOW;

void setup() {
  pinMode(ledPin, OUTPUT);
  pinMode(interruptPin, INPUT_PULLUP);
  attachInterrupt(digitalPinToInterrupt(interruptPin), blink, CHANGE);
}

void loop() {
  digitalWrite(ledPin, state);
}

void blink() {
  state = !state;
}
```

Interrupt Numbers

Normally you should use `digitalPinToInterrupt(pin)`, rather than place an interrupt number directly into your sketch. The specific pins with interrupts, and their mapping to interrupt number varies on each type of board. Direct use of interrupt numbers may seem simple, but it can cause compatibility trouble when your sketch is run on a different board.

However, older sketches often have direct interrupt numbers. Often number 0 (for digital pin 2) or number 1 (for digital pin 3) were used. The table below shows the available interrupt pins on

[SIGN IN](#) [HOME](#) [STORE](#) [SOFTWARE](#) [EDUCATION](#) [RESOURCES](#) [COMMUNITY](#) [HELP](#)[attachInterrupt\(\)](#)

BOARD	INT.0	INT.1	INT.2	INT.3	INT.4	INT.5
Uno, Ethernet	2	3				
Mega2560	2	3	21	20	19	18
32u4 based (e.g Leonardo, Micro)	3	2	0	1	7	

For Uno WiFiRev.2, Due, Zero, MKR Family and 101 boards the **interrupt number** = **pin number**.

See also

LANGUAGE [detachInterrupt\(\)](#)

NEWSLETTER

ENTER YOUR EMAIL TO SIGN UP

SUBSCRIBE

[Terms Of Service](#)

[Privacy Policy](#)

[Contact Us](#)

[About Us](#)

[Distributors](#)

[Careers](#)

[Security](#)